

# Traktor LE 2 Generic MIDI Chart

On the setup wizard, select Vestax VCI-100

Control	Note/CC	Ch.	Type
Main Level	7	1	CC
Crossfader	8	1	CC
Deck A Volume	12	1	CC
Deck B Volume	13	1	CC
Deck A Pitch Fader	14	1	CC
Deck B Pitch Fader	15	1	CC
Deck A Scrub	18	1	CC
Deck B Scrub	19	1	CC
Deck A Hi EQ	20	1	CC
Deck A Mid EQ	21	1	CC
Deck A Low EQ	22	1	CC
Deck A Filter	23	1	CC
Deck B Hi EQ	24	1	CC
Deck B Mid EQ	25	1	CC
Deck B Low EQ	26	1	CC
Deck B Filter	27	1	CC
Deck A Gain	28	1	CC
Deck B Gain	29	1	CC
Deck A Pan	30	1	CC
Deck B Pan	31	1	CC
FX 1 Dry/Wet	70	1	CC
FX 1 Knob 1	71	1	CC
FX 2 Dry/Wet	74	1	CC
FX 2 Knob 1	75	1	CC
FX 1 Dry/Wet	84	1	CC
FX 1 Knob 1	85	1	CC
FX 2 Dry/Wet	86	1	CC
FX 2 Knob 1	87	1	CC
Headphones Volume	88	1	CC
Headphones Mix	89	1	CC
Deck A Play	D4 (50)	1	Note
Deck A CUP	D#4 (51)	1	Note
Deck A CUE	E4 (52)	1	Note
Deck B Play	F#4 (54)	1	Note
Deck B CUP	G4 (55)	1	Note
Deck B CUE	G#4 (56)	1	Note
Deck A Pitch Bend Up	A#4 (58)	1	Note
Deck A Pitch Bend Down	B4 (59)	1	Note
Deck B Pitch Bend Up	C5 (60)	1	Note
Deck B Pitch Bend Down	C#5 (61)	1	Note
Deck A Loop Active	F#5 (66)	1	Note
Deck B Loop Active	G5 (67)	1	Note
Deck A Key Lock	G#5 (68)	1	Note
Deck B Key Lock	A5 (69)	1	Note
Deck A Sync	A#5 (70)	1	Note
Deck B Sync	B5 (71)	1	Note
Deck A Prelisten	C6 (72)	1	Note
Deck B Prelisten	C#6 (73)	1	Note
FX 2 On/Off	E6 (76)	1	Note
FX 1 Effect Swap UP	F6 (77)	1	Note
FX 2 Effect Swap UP	F#6 (78)	1	Note
FX 1 Effect Swap DOWN	G#6 (80)	1	Note
FX 2 Effect Swap DOWN	A6 (81)	1	Note
FX 1 On/Off	D7 (86)	1	Note
FX 2 On/Off	D#7 (87)	1	Note
File Browser UP	G#7 (92)	1	Note
File Browser Down	A7 (93)	1	Note
Load in Preview	A#7 (94)	1	Note
Load in Deck A	C8 (96)	1	Note
Load in Deck B	C#8 (97)	1	Note
Browser Tree Up	D8 (98)	1	Note
Browser Tree Down	D#8 (99)	1	Note